

NSE7_PBC-6.4^{Q&As}

Fortinet NSE 7 - Public Cloud Security 6.4

Pass Fortinet NSE7_PBC-6.4 Exam with 100% Guarantee

Free Download Real Questions & Answers **PDF** and **VCE** file from:

https://www.leads4pass.com/nse7_pbc-6-4.html

100% Passing Guarantee
100% Money Back Assurance

Following Questions and Answers are all new published by Fortinet
Official Exam Center

-  **Instant Download** After Purchase
-  **100% Money Back** Guarantee
-  **365 Days** Free Update
-  **800,000+** Satisfied Customers



QUESTION 1

What is the bandwidth limitation of an Amazon Web Services (AWS) transit gateway VPC attachment?

- A. Up to 1.25 Gbps per attachment
- B. Up to 50 Gbps per attachment
- C. Up to 10 Gbps per attachment
- D. Up to 1 Gbps per attachment

Correct Answer: A

Reference: <https://d1.awsstatic.com/whitepapers/building-a-scalable-and-secure-multi-vpc-aws-networkinfrastructure.pdf> (5)

QUESTION 2

You have been tasked with deploying FortiGate VMs in a highly available topology on the Amazon Web Services (AWS) cloud. The requirements for your deployment are as follows:

You must deploy two FortiGate VMs in a single virtual private cloud (VPC), with an external elastic load balancer which will distribute ingress traffic from the internet to both FortiGate VMs in an active-active topology.

Each FortiGate VM must have two elastic network interfaces: one will connect to a public subnet and other will connect to a private subnet.

To maintain high availability, you must deploy the FortiGate VMs in two different availability zones.

How many public and private subnets will you need to configure within the VPC?

- A. One public subnet and two private subnets
- B. Two public subnets and one private subnet
- C. Two public subnets and two private subnets
- D. One public subnet and one private subnet

Correct Answer: A

QUESTION 3

The output is simplified for clarity.

```
config route
  edit "SSTENTAZFGT-0302-Nic-01"
    config ip
      edit "SSTENTAZFGT-0302-Nic-01"
        set public-ip "SSTENTAZFGT-03-FloatingPIP"
      next
    end
  next
end
config route-table
  edit "FortigateUDR-01"
    config route
      edit "defaultroute"
        set next-hop "172.29.32.71"
      next
      edit "RouteToSST-ENT-AZ-Demo-03-vNet01-Subnet-07"
        set next-hop "172.29.32.71"
      next
      edit "RouteToSST-ENT-AZ-Demo-03-vNet01-Subnet-08"
        set next-hop "172.29.32.71"
      next
    end
  next
end
end
SSTENTAZFGT-0302 #
```


Refer to the exhibit. Consider an active-passive HA deployment in Microsoft Azure. The exhibit shows an excerpt from the passive FortiGate-VM node.

If the active FortiGate-VM fails, what are the results of the API calls made by the FortiGate named SSTENTAZFGT-0302? (Choose two.)

- A. SSTENTAZFGT-03-FloatingPIP is assigned to the IP configuration with the name SSTENTAZFGT0302-Nic-01, under the network interface SSTENTAZFGT-0302-Nic-01
- B. 172.29.32.71 is set as a next hop IP for all routes under FortigateUDR-01
- C. The network interface of the active unit moves to itself
- D. SSTENTAZFGT-03-FloatingPIP public IP is assigned to NIC SSTENTAZFGT-0302-Nic-01

Correct Answer: AB

QUESTION 4



Refer to the exhibit. The exhibit shows a topology where multiple connections from clients to the same FortiGate-VM instance, regardless of the protocol being used, are required.

Which two statements are correct? (Choose two.)

- A. The design shows an active-active FortiGate-VM architecture.
- B. The Cloud Load Balancer Session Affinity setting should be changed to CLIENT_IP.
- C. The design shows an active-passive FortiGate-VM architecture.
- D. The Cloud Load Balancer Session Affinity setting should use the default value.

Correct Answer: AB

QUESTION 5

Your company deploys FortiGate VM devices in high availability (HA) (active-active) mode with Microsoft Azure load balancers using the Microsoft Azure ARM template. Your senior administrator instructs you to connect to one of the FortiGate devices and configure the necessary firewall rules. However, you are not sure how to obtain the correct public IP address of the deployed FortiGate VM and identify the access ports.

How do you obtain the public IP address of the FortiGate VM and identify the correct ports to access the device?

- A. In the configured load balancer, access the inbound NAT rules section.
- B. In the configured load balancer, access the backend pools section.
- C. In the configured load balancer, access the inbound and outbound NAT rules section.

D. In the configured load balancer, access the health probes section.

Correct Answer: C

Reference: <https://www.fortinet.com/content/dam/fortinet/assets/deployment-guides/dg-fortigate-highavailability-azure.pdf>

[NSE7_PBC-6.4 PDF Dumps](#)

[NSE7_PBC-6.4 Practice
Test](#)

[NSE7_PBC-6.4 Exam
Questions](#)