

## C9010-022<sup>Q&As</sup>

IBM AIX Administration V1

**Pass IBM C9010-022 Exam with 100% Guarantee**

Free Download Real Questions & Answers **PDF** and **VCE** file from:

<https://www.leads4pass.com/c9010-022.html>

100% Passing Guarantee  
100% Money Back Assurance

Following Questions and Answers are all new published by IBM Official Exam Center

-  **Instant Download** After Purchase
-  **100% Money Back** Guarantee
-  **365 Days** Free Update
-  **800,000+** Satisfied Customers



**QUESTION 1**

A host is already configured to access the network, and the administrator would like to configure a second adapter on the same system. This adapter should be permanently configured so that the new IP address is available when the system reboots. Which command should be used?

- A. ifconfig
- B. ipconfig
- C. mktcpip
- D. chdev

Correct Answer: D

---

**QUESTION 2**

What is a mandatory requirement to allow an AIX 7-based NIM Master to install clients over IPv6?

- A. The NIM Master must use static IPv6 addresses.
- B. The NIM Master must have both IPv4 and IPv6 connectivity.
- C. The NIM Master must be installed with the AIX Enterprise Edition license.
- D. The NIM Master must be running at least AIX 7.1 TLOO Service Pack3 or later.

Correct Answer: A

---

**QUESTION 3**

What action does the following command perform for a new AIX hdisk, hdisk1 ?

```
chdev -l hdisk1 -a pv=yes
```

- A. Makes the disk available for use
- B. Changes the existing pvid on the disk to Yes\\'
- C. Sets the physical volume identifier
- D. Clears volume group locks
- E. Resets the volume group descriptor area

Correct Answer: C

---

**QUESTION 4**

Given the following topas output:

```
topas Monitor for host:
Interval: 2
CPU      User%  Kern%  Wait%  Idle%  Physc  Entc%
Total    0.2   1.6   0.0   98.1   0.01   3.17
Network  I-Pkts  O-Pkts  B-In  B-Out
Total    2.09K  6.00   1.50  346.0  1.76K
Disk     Busy%   IOPS   TPS  B-Read  B-Writ
Total    0.8    46.0K  11.00  0      46.0K
FileSystem IOPS   TPS  B-Read  B-Writ
Total    0      0      0      0
EVENTS/QUEUES  FILE/TTY
Cswitch        187  Readch        0
Syscall        121  Writech       311
Reads           0  Rawin         0
Writes          0  Ttyout       311
Forks           0  Igets         0
Execs           0  Namei         1
Runqueue       1.50  Dirblk        0
Waitqueue       0.0
PAGING
Faults          0  Real,MB      1024
Steals          0  % Comp       59
PgspIn          0  % Noncomp    18
PgspOut         0  % Client     18
```

What does the Entc% value represent?

- A. Percentage of Ethernet consumed
- B. Performance statistics for all logical CPUs in the system
- C. Percentage of physical capacity consumed
- D. Percentage of entitled capacity consumed

Correct Answer: D

### QUESTION 5

An LPAR is hosted on Power8 hardware.

How can an adapter assigned as "required" to that LPAR be removed with minimal downtime?

- A. Initiate the Add/Remove procedure from the ASMI
- B. Use the CHARM tool to remove the adapter
- C. Remove the device throughdiag, and DLPAR remove the adapter
- D. Remove the required setting in the profile, and DLPAR remove the adapter

Correct Answer: D

[Latest C9010-022 Dumps](#)

[C9010-022 Study Guide](#)

[C9010-022 Exam Questions](#)